

So installieren Sie die aktuelle Version der NRE Software unter Linux

Sinnvoll ist es, die NetWorker Dienste zu stoppen. Dann ist, wie unter Linux üblich, die vorhandene Software zu entfernen und anschließend die neue zu installieren.

Auf der nächsten Seite führe ich die einzelnen Schritte detailliert auf.

```

login as: root
root@centos81-neu's password:
Activate the web console with: systemctl enable --now cockpit.socket

Last login: Mon Mar  8 21:44:45 2021
[root@centos81-neu ~]# cd /software
[root@centos81-neu nw_19_4_0_0]# ls -la
total 159220
drwxr-xr-x. 3 root root      130 Mar 28 12:41 .
drwxr-xr-x. 5 root root       52 Mar  8 21:47 ..
drwxr-xr-x. 2 root root    4096 Jan 17 15:48 linux_x86_64
-rw-r--r--. 1 root root 1611219 Nov 16 18:11 NetWorkerVolumeMove100_linux_x86_64.tar.gz
-rw-r--r--. 1 root root 80585349 Nov 16 18:07 nre-linux-8.0.7.rpm
-rw-r--r--. 1 root root 80832365 Mar 26 23:32 nre-linux-8.0.8.rpm
[root@centos81-neu nw_19_4_0_0]#
[root@centos81-neu nw_19_4_0_0]# systemctl stop networker
[root@centos81-neu nw_19_4_0_0]#
[root@centos81-neu nw_19_4_0_0]# rpm -qa | grep nre
nre-8.0.7-1.x86_64
[root@centos81-neu nw_19_4_0_0]#
root@centos81-neu nw_19_4_0_0]# rpm -e nre-8.0.7-1.x86_64
[root@centos81-neu nw_19_4_0_0]#
[root@centos81-neu nw_19_4_0_0]# rpm -ivh nre-linux-8.0.8.rpm
Verifying...                               ##### [100%]
Preparing...                               ##### [100%]
Updating / installing...
 1:nre-8.0.8-1                               ##### [100%]
      NOTE: To complete configuration execute the following script :
            /opt/nre/nreconfig.sh
[root@centos81-neu nw_19_4_0_0]#
[root@centos81-neu nw_19_4_0_0]# /opt/nre/nreconfig.sh

Creating the installation log in /opt/nre/logs/install.log.

Performing initialization. Please wait...

NRE configuration completed
[root@centos81-neu nw_19_4_0_0]#
[root@centos81-neu nw_19_4_0_0]#

```